## **MODECOM FREETAB 8001 HD X2**

## Firmware updates >>> Android 4.2.2 Jelly Bean >>> Version 1

- Before updating charge the tablet
- Updates erases all data from the device
- Please carry out updating proces in accordance
- To run an update computer and micro usb connector (included) are required
- Windows XP requires an update PhoenixSuit to version 1.0.6

The first launch of the device after the update may take a little longer than normally (a few minutes), as it is connected with the installation of the components.

- 1. Prepare tablet and micro usb cable which is included in the set
- 2. From the following link download the file containing updated to Android 4.2.2 Version 1

http://freetab.eu/softy/ENG/Tablets/FreeTAB 8001 HD X2/Firmware/Android 4.2.2/Version 1/EN/Firmware 8001 android 4.2.2 version 1.zip

- **3.** Unzip the file **Firmware\_8001\_android\_4.2.2\_version\_1.zip** on computer disk drive, a folder named Firmware\_8001\_android\_4.2.2\_version\_1 will be created
- 4. Run the file PhoenixSuit\_EN.msi from PhoenixSuit\_v.1.0.5 folder

						x
Coo v 📔 « Firmv	vare_f	freetab_9704	5 🗸 😽	Przeszukaj: Phoeni	xSuit_v1.0.5	<b>م</b>
Organizuj 🔻 Umie	ść w l	bibliotece 🔻 Udostępnij 💌	Nagraj No	wy folder	· · ·	0
🔶 Ulubione	<u>^</u>	Nazwa		Data modyfikacji	Тур	
📃 Pulpit		뤻 PhoenixSuit_EN		2013-02-18 13:46	Pakiet Instalate	ora
Statnie miejsca	Ш					
🥽 Biblioteki						
Apps						
Dokumenty						
J Muzyka						
📑 Wideo	-	٠				F
1 element						


PhoenixSuit
Welcome to the PhoenixSuit Setup Wizard
The installer will guide you through the steps required to install PhoenixSuit on your computer.
WARNING: This computer program is protected by copyright law and international treaties. Unauthorized duplication or distribution of this program, or any portion of it, may result in severe civil or criminal penalties, and will be prosecuted to the maximum extent possible under the law.

😸 PhoenixSuit	X
Select Installation Folder	<b>-</b>
The installer will install PhoenixSuit to the following folder.	
To install in this folder, click "Next". To install to a different folder, enter it below or click "Bro	wse".
Eolder: C:\Program Files (x86)\AllWinnertech\ Disk Cos	
Install PhoenixSuit for yourself, or for anyone who uses this computer:	
everyone	
⊚ Just me	
Cancel < Back Nex	xt >

提 PhoenixSuit	
Confirm Installation	
The installer is ready to install PhoenixSuit on your computer.	
Click "Next" to start the installation.	
Cancel < Back	Next >

岁 PhoenixSuit	
Installing PhoenixSuit	
PhoenixSuit is being installed.	
Please wait	
Cancel < Back	Next >

Device Driver Installation Wizard	1		
	Installatio	to the Device Driver on Wizard! a you install the software drivers that some as need in order to work.	
	[	< Wstecz Dalej > Anuluj	
			Cancel < Back Next >



Device Driver Installation Wiza	rd	)
	Completing the Device Driver Installation Wizard   The drivers were successfully installed on this computer.   Driver Name Status   ✓ Google, Inc. (WinUSB) Device Updated   < Wstecz Zakończ Anuluj	
		iancel < Back Next >
PhoenixS	Intion Complete uit has been successfully installed. se" to exit.	

5. Run the program **PhoenixSuit** and go to the **Firmware** click **Image** and select the update file **Firmware\_8001\_android\_4.2.2\_version\_1.img** in the folder Firmware\_8001\_android\_4.2.2\_version\_1

Cancel


< Back

Close


## Warning! After selecting the file, do not click on the button Upgrade


PhoenixSuit A Convinced Firmware Tool Home Firmware Apk New	
Please Select the Image File First Upgrade	
Caution: Please Check the Device Power Before Upgrade. Do not Unplug Device during the Upgrade Procedure.	
No Device Attach!	Phoenix Suit V1.0.6


Otwieranie	Firmware_MODEL_a	P		++ Przeszukaj: Firm	ware_MODEL P
Organizuj 🔻 Nowy fold	der			1	: • 🔟 🔞
Image: System (C:)   Image: System (C:)	Firmware_N	t v1.0.5 AODEL_android_	VERSION	Data modyfikacji 2013-08-28 15:59 2013-07-22 11:51	Typ Folder plików Plik obrazu dysku
	nplug Device durin	g the Upgrade	Procedure.	Otwórz 🚽	Anuluj
lo Device Attach!					Phoenix Suit V1.0



- 6. Turn off the tablet with android system level or press the Home button simultaneously and hold down the Power and about 10 seconds, the tablet is turned off. Press and hold down the button Home for 10 seconds, while keeping the button pressed Home, connect your tablet to your computer with usb cable, after its merger still holding down the Home button, press the Power button 3x. Release the pressure from the Home, tablet will be detected by the system, which will begin automatically install the drivers, necessary to carry out firmware updates, process may take several minutes. Meanwhile various system information will appear in the right bottom corner of the system (clouds with drivers installation information etc.)
- 7. After the system installs the drivers automatically, program PhoenixSuit will display question concerning formatting memory of the tablet please click **Yes**, program will start firmware update procedure, wait few minutes, do not disconnect tablet from the computer







The software has been properly installed, disconnect the device from the computer

